



ViewStick 2 Software Update



To get the latest ViewStick 2 features, a regular software update is recommended

You can find the “Download software” on vsweb.us/viewstick2

1 STEP 1: UPDATE THE VIEWSTICK 2 DONGLE

Option 1: via USB stick

1. Download new software from vsweb.us/viewstick2, named “ViewStick 2 Firmware”
2. Rename the img file to install.img and copy it onto the USB stick
3. Plug the USB stick into the female USB port of Y cable
4. Connect to the Wi-Fi of ViewStick 2. The default SSID is “ViewStick 2 XXX”
5. Browse to the wireless IP address of the ViewStick 2 dongle: 192.168.59.254
Enter the password “admin”
6. Go to “Remote Control”, “Setting” button, “System” shift, then “USB Upgrade to upload the new software which you have saved on your USB stick
7. The upload is in progress and the Base Unit is verifying the Update Package
8. Installing Update Package
9. After software update has completed, the ViewStick 2 Dongle will automatically reboot




Option 2: via internet

1. Connect to the Wi-Fi of ViewStick 2. The default SSID is “ViewStick 2 XXX”
2. Browse to the wireless IP address of the ViewStick 2 dongle: 192.168.59.254
Enter the password “admin”
3. Go to “Wireless Settings”, “Wifi Connection” shift, “Scan AP” button to scan the AP, choose the AP which is connected to the internet, enter the password if there is



4. Connect to the Wi-Fi of step 3 connected
5. Browse to the wireless IP address of the ViewStick 2 dongle: show on ViewStick 2 screen
Enter the password “admin”
6. Go to “Firmware Upgrade”, then “On-line upgrade” to check the latest version of version
7. The download is in progress
8. Installing Update Package
9. After software update has completed, the ViewStick 2 Dongle will automatically reboot




2 STEP 2: UPDATE THE SOFTWARE ON COMPUTER/MOBILE

Windows/Mac Computer Option 1: via internet

1. Download new software from vsweb.us/viewstick2, named “Windows/Mac Software”
Extract the zip file
2. Use Install file and follow the instruction to update new software

Windows/Mac Computer Option 1: via software

1. Login software to ViewStick 2
2. Go to “Menu”, “Software Update” to check latest version, then “Download update”
3. “Extract” to open the file document
4. Use Install file and follow the instruction to update new software



Mobile iOS:

1. The App Store will auto detect to update AutoProject app

Mobile Android:

1. The Google Play will auto detect to update AutoProject app